eTIR web services Introduction document





Table of Contents

1.	Document revision note	. 1
2.	Purpose	. 1
З.	Target audience	. 1
4.	Prerequisites	. 1
5.	eTIR documentation walkthrough	. 1
6.	eTIR web service overview	. 3
	6.1. High level architecture	. 3
	6.2. Interface message overview	. 4
	6.3. TIR transport and TIR operation in eTIR	. 6
	6.4. eTIR sequence diagrams	. 7
	6.4.1. Message sequence for countries of departure	. 7
	6.4.2. Message sequence for countries of transit	. 8
	6.4.3. Message sequence for countries of destination	. 9
7.	Security aspects	10
	7.1. eTIR security model	10
	7.2. Authentication, Integrity and Non-repudiation	11
	7.2.1. Authentication steps using an X.509 certificate	11
	7.2.2. Key pairs generation	12
	7.3. Confidentiality	12
8.	Access to eTIR web services.	13
	8.1. Prerequisites	13
	8.1.1. Network requirements	13
	8.1.2. Certificates	13
	8.1.3. Whitelisting servers	13
	8.2. Endpoint URLs	14
9.	Implementation and test of eTIR messages	15
	9.1. Recommended general approach	15
	9.1.1. Purpose	15
	9.1.2. General approach	15
	9.1.3. Continuous Integration	15
	9.1.4. Extensive testing	15
	9.2. Tool kit: list of what we believe is useful	15
	9.3. SOAP Header generation	16
	9.3.1. Web service addressing header elements	16
	9.3.2. Security element	17
	9.3.3. SOAP eTIR message example	24
	9.4. Implementation of MetaData fields	25
	9.4.1. Field details	25
	9.4.2. Field descriptions & usages	25
	9.5. Implementation of the numerical fields	27
	9.6. Implementation of the text fields	27
	9.7. Implementation of coded fields	28
	9.8. Implementation of the date fields	28
	9.8.1. Fields with dates only	28
	9.8.2. Fields with dates and time	30

9.9. Implementation of the Message Identifier / Original Message Identifier	31
9.9.1. General	31
9.9.2. Request message	31
9.9.3. Response message.	32
9.10. Implementation of the Sequence number attributes	32
9.11. Implementation of the Measurement sub-attributes	32
9.12. Validation mechanism	33
9.13. Error management	33
9.13.1. Introduction to error management	33
9.13.2. Presentation of error codes	33
9.13.3. Sample errors	34
9.13.4. Error handling	35
10. Fallback procedures	36
11. Support and contact	36
12. Annexes	37
12.1. Version history	37
12.2. Glossary	38
12.3. Technical summary	42
12.4. KeyStore: step by step generation of key pairs	43
12.4.1. Using the KeyStore Explorer application	43
12.4.2. Using the Keytool command line interface	47
12.5. SOAP UI quick guide.	50
12.5.1. Procedure	50
12.5.2. Troubleshooting	56
"A security error was encountered when verifying the message"	56
12.6. Example of SOAP request using WSS4J	57





1. Document revision note



This document has been published on **22/09/2021**, and is valid for the **eTIR international system version 1.0** based on the **eTIR specifications version 4.3.0**.

Please ensure you get the latest version of this document from the eTIR documentation portal or contact the eTIR service desk (Support and contact).

2. Purpose

This document describes the eTIR international system web services, in particular: the intended target audience, the system architecture, the various messages and their sequencing, the security aspects, the accesses as well as the support contacts. It does not cover the detailed implementation required for each message, which can be found in the documents dedicated to each of the eTIR messages. Rather, it describes which components and processes should be put in place in the national customs systems to effectively interconnect with the eTIR international system.

3. Target audience

This guide is intended for the customs ICT team in charge of TIR processes and in charge of interconnecting with their national customs systems with the eTIR international system.

4. Prerequisites

This document is to be read after having an understanding of the eTIR concepts, and after having read and followed the Project guidelines for customs to connect to eTIR. It is most important to understand the implementation stages described in the above guidelines, and to understand where you currently stand in the implementation process.



In order to ensure an implementation that delivers the best value and services to the customs authorities, we highly recommend the ICT team to be accompanied by a TIR subject matter expert, as mentioned in the Project guidelines for customs to connect to eTIR.

5. eTIR documentation walkthrough

The eTIR international system relies on the TIR Convention, and as such the eTIR documentation relies on its articles and annexes, but also on various other key documents available online and introduced below. Some of these documents must be read and well understood while others are reference documents to be consulted when necessary. This section will help you understand what they contain and in which order we recommend reading them.

1. Project guidelines for Customs to connect to eTIR: this document is the starting point for the customs authorities of any contracting party and should be read before any other one.

If you are not familiar with the transport and border crossing facilitation problematics, we highly encourage you to read:

2. The TIR Convention handbook: this document contains all the legal elements that rule the TIR Convention (including Comments and Explanatory Notes). It also describes the processes to be followed by customs authorities, national associations and TIR Carnet holders.





3. Annex 11 to the TIR Convention: Annex 11 to the TIR Convention describes the eTIR procedure, how processes shall be adapted to be computerized and set the legal provisions for the implementation and usage of the eTIR international system.

Once the TIR legal context and key processes are well understood, we strongly advise to read:

- 4. The introduction to the eTIR conceptual, functional and technical documentation: this document introduces the conceptual, functional and technical documentation for the TIR Procedure Computerization Project in accordance with the United Nations Centre for Trade Facilitation and Electronic Business (UN/CEFACT) Modelling Methodology. It is the first document to be read in order to approach how eTIR was envisioned as an extension of the TIR Convention.
- 5. The eTIR concepts: this document describes the approach and core concepts used to support the business logic, and to implement the eTIR international system. This document is also a reference document that describes all the use cases and all the business rules used for the technical implementation.
- 6. The eTIR functional specifications: this document is the most important to read to get a deep understanding of the mechanisms used to implement the eTIR international system. The current version (4.2) is being expanded in a working document (4.3.0) and refined as the work progresses and as feedback is received from modelling work carried out by the Informal Ad hoc Expert Group on Conceptual and Technical Aspects of Computerization of the TIR Procedure (GE.1) and all the eTIR focal points. These specifications (once called Reference Model) also refer to the following additional documents and lists:
 - a. eTIR XML schemas
 - b. eTIR code lists
 - c. eTIR error code list
- 7. Finally, if you wish to contact other contracting parties during this implementation, please refer to the The eTIR Focal Points page to find their contact information.



6. eTIR web service overview

6.1. High level architecture

The eTIR international system is based on the following functional overview diagram:





Kindly note the following acronyms meanings:

B2B: Business to Business relationship (where business refers to the private sector).
C2B: Customs to Business relationship (where business refers to the private sector).
B2C: Business to Customs relationship (where business refers to the private sector).
C2C: Customs to Customs relationship.

Technology stack:

The eTIR international system has been implemented using the following technologies:

- Java programming language
- PostgreSQL database
- Spring framework
- ActiveMQ
- SOAP-XML web services
- Apache CFX
- Apache Camel







Although these technologies are only listed for information, if the reader has any questions on the implementation methods and or on the technology stack used to implement the eTIR international system, please contact the eTIR service desk at etir@un.org.

The eTIR international system exposes secured web service endpoints with both the public and the private sector partners following the diagram below:





Note that at the moment there is only one guarantee chain in activity (namely the International Road Transport Union) but that the TIR Convention does not limit it to one.

6.2. Interface message overview

The list of eTIR messages are categorized internally, based on the message sender/addressee and based on message direction (eTIR centric):

- All messages codes start either:
 - by "I" for Internal (Internal to the public sector, meaning between the eTIR international system and either national customs systems or ITDB)
 - by "E" for External (External to the public sector, meaning between eTIR and either a guarantee chain or a TIR Carnet holders)
- All messages work by pair (request-response), and their codes all end either:
 - by an "odd number" for the initiating/calling/request message
 - by an "even number" for the response/acknowledgment message



Find below the list of all internal and external messages:

External messages	Internal messages
• E1 - Register guarantee	 I1 - Accept guarantee
 E2 - Registration results 	 I2 - Acceptance results
• E3 - Cancel guarantee	 I3 - Get holder information
 E4 - Cancellation results 	 I4 - Holder information
• E5 - Query guarantee	 I5 - Query guarantee
 E6 - Query results 	 I6 - Query results
• E7 - Notify guarantee chain	 I7 - Record declaration data
 E8 - Notification confirmation 	 I8 - Record declaration data results
• E9 - Advance TIR data	 I9 - Start TIR operation
 E10 - Advance TIR data results 	 I10 - Start results
• E11 - Advance amendment data	 I11 - Terminate TIR operation
 E12 - Advance amendment data results 	 I12 - Termination results
• E13 - Cancel advance data	 I13 - Discharge TIR operation
 E14 - Cancel advance data results 	 I14 - Discharge results
	 I15 - Notify customs
	 I16 - Notification confirmation
	 I17 - Refusal to start TIR operation
	 I18 - Refusal results
	 I19 - Check customs offices
	 I20 - Customs offices validation

The eTIR international system aims to ensure the secure exchange of data between the national customs systems related to the international transit of goods, vehicles or containers according to the provisions of the TIR Convention and to allow customs to manage the data on guarantees, issued by guarantee chains, to holders authorized to use the TIR system.



1



6.3. TIR transport and TIR operation in eTIR

The diagram below highlights the important concepts of **TIR transport** and **TIR operations** and gives an example of them:



It is important to note that a TIR transport may have multiple loading and unloading points, and of course multiple border crossings. Each of them separates the TIR operations. Also note that the border crossings separating the TIR operations are between each customs territories (that can be a country, or a common customs territory like in case of the European Union). More details can be found in the dedicated page of the eTIR introduction document.

Example of a TIR transport







6.4. eTIR sequence diagrams

The usage of the eTIR messages is described in the following eTIR sequence diagrams for countries of departure, transit and destination:

6.4.1. Message sequence for countries of departure







6.4.2. Message sequence for countries of transit





6.4.3. Message sequence for countries of destination







7. Security aspects

The eTIR international system web services use WS-Security to electronically sign the messages. WS-Security is not used to provide encryption of the message. This framework has been released as a full industry-recognized recommendation in March 2004.

Digital signature, using X.509 certificates (version 3), are used to identify the caller to the web service and provide non-repudiation capability. An encryption protocol (TLS v1.2 or v1.3) is used to send the messages over HTTPS to ensure the confidentiality of the information exchanged in the messages. It should be noted that the digital signature and the encryption protocol (TLS) use different asymmetric key pairs.

The next paragraphs describe the web services, security related terms and concepts that are used throughout this document. They often refer on the terms "Web Services Security (WS-Security)", "X.509 token", "keystore" and "truststore" which are explained in detail in the Glossary.

7.1. eTIR security model

The figure below depicts the WS-Security model and this section provides an overview illustrating how this security model works.





Kindly note that if this diagram represents most of the use cases, in a few other cases the eTIR international system actually play the role of client, and the national customs systems, the role of service provider.

In the example above, as a first step, the X.509 certificate of the national customs systems will be installed in the eTIR international system truststore. Similarly, the eTIR international system certificate will be installed in the national customs systems truststore. This mandatory initial step allows the validation of the digital signatures that are transferred as security tokens in all SOAP messages exchanged in the context of the eTIR procedure.

Kindly find below a description of how a request is sent by the national customs systems to the eTIR international system, and how the related response is sent back:

1. The national customs systems generate a request message to be sent to the eTIR international system web service.



- 2. The request message is signed with the private key of the national customs systems' X.509 certificate (stored in the keystore) and sent using an encryption protocol (TLS) over HTTPS.
- 3. The eTIR international system receives the request message, verifies the signature of the message using the public key of the sender to authenticate it and to confirm its integrity.
- 4. The eTIR international system processes the request message and generates a response message in return.
- 5. The response message is signed with the private key of the eTIR international system (stored in the keystore) and sent using an encryption protocol (TLS) over HTTPS.
- 6. The national customs systems receive the response message, and verify the signature of the message using the public key of the service provider to authenticate it and to confirm its integrity.

The completion of this process illustrates the implementation of four security aspects that the eTIR international system wishes to achieve with this security model: **authentication**, **integrity**, **confidentiality** and **non-repudiation**.

7.2. Authentication, Integrity and Non-repudiation

Authentication is used to ensure that the different parties of a transaction are really who they claim to be; thus, a proof of identity is required. This proof can be claimed in various ways. One simple example is to provide a user ID together with a secret password. A more secured approach is to use an X.509 certificate issued from a trusted Certificate Authority (later referred as "CA" in this section). The X.509 certificate identifies the end user. In addition to the authentication feature, the private key to the X.509 certificate is also used to sign SOAP messages. This electronic signature not only ensures the identity of the sender but also guarantees that the message content has not been tampered during the transmission, thus ensuring integrity. The sender uses his private key to sign the message (the hash of the message to be more precise) and the recipient of the message uses the sender's public key to verify the signature, thus providing proofs of non-repudiation.

7.2.1. Authentication steps using an X.509 certificate



The client application (national customs systems) sends a message to the service provider (eTIR international system - Step #1). The message includes the client application's credentials, signed with the private key that is paired with the public key in the client application's X.509 certificate. The service provider validates the certificate by performing a number of checks (Step #2), including:

- Verifying that the certificate has not expired. If the expiration date of the certificate is past due, then the certificate is no longer valid.
- Verifying that the certificate is internally consistent. The service checks that the data in the certificate has not been tampered with by verifying the certificate contents against the signature of the issuing CA.
- Verifying the issuing CA of the client's X.509 certificate. This is done by comparing the issuer's signature on the client application's X.509 certificate with the X.509 certificate of the issuing CA.





For this step to work properly, the CA that issued the client's X.509 certificate must be trusted by both the client application and the service provider.

- Verifying that the issuing CA has not revoked the certificate. The service provider checks this by making sure that the X.509 certificate does not appear on a Certificate Revocation List (CRL) published by the issuing CA. The service can check the revocation status of the certificate by directly accessing it from the CA or by checking against a CRL that was previously downloaded from the issuing CA to the certificate repository used by the service to look up X.509 certificates.
- The service provider uses the public key in the client application's X.509 certificate to verify the client application's signature (Step #3). This allows the service provider to authenticate the client application and to ensure that the signed data has not been tampered with after the message was signed.

If the authentication is unsuccessful, the service provider then returns an HTTP 500 error message. If it is successful, it will process the content of the request and produce the appropriate response message following the eTIR specifications (Step #4) that will, upon reception, require the same checks described above (Step #5).

7.2.2. Key pairs generation

Customs can obtain a public and private key pair from a trusted certificate authority or create selfsigned ones. They should generate an RSA key pair and provide to the UNECE TIR secretariat team the public part (X.509 certificate) of the generated key and keep the private key well protected in their keystore. See in the Annexes the description of the two ways to generate an RSA key pair.

7.3. Confidentiality

The HyperText Transfer Protocol Secure (HTTPS), used to access the eTIR international system endpoints, is an extension of the HyperText Transfer Protocol (HTTP) where communication is encrypted using Transport Layer Security (TLS), a cryptographic protocol designed to provide communications security over public networks like the Internet. The principal reason for using HTTPS is the need to ensure confidentiality and integrity of the exchanged data while in transit. It protects against information security threats like the Man-in-the-middle attack. The bidirectional encryption of communications between a client and server protects against from eavesdropping and tampering of the communication. Therefore, communication between the eTIR international system and the national customs systems is secured by the bidirectional encryption using TLS (at least v1.2).



8. Access to eTIR web services

8.1. Prerequisites

8.1.1. Network requirements

The national customs systems must have access to the Internet and all the domains of the User Acceptance Testing and Production environments described in the section below should be whitelisted by the Network engineers of the customs authorities. In addition, in the eTIR international system context, SOAP is implemented to use HTTPS on port TCP/8083, therefore this protocol and port should be opened in the firewalls of the customs authorities to be usable by the national customs systems.

8.1.2. Certificates

As explained in the Security aspects section, the connection between the eTIR international system and the national customs systems requires both parties to share their X.509 certificates and to mutually store them in their truststores.

This procedure must be completed for each client-service environment pair during the implementation phase, the national customs systems User acceptance Testing (UAT) environment should be connected to the eTIR international system UAT environment. Once ready for production, both parties Production environments should exchange their dedicated Production X.509 certificates to allow for communication between them and usage of the eTIR procedure when the launch is confirmed.



Both systems (the eTIR international system and national customs systems) should use different X.509 certificates for their respective UAT and Production environments. Also note that if this documentation refers to methods to generate locally certificates using an open-source application that may be useful for test and development purposes, the certificates generated and shared by the customs ICT team is entirely up to their choice so long as it respects the security requirements and aspects mentioned in this document.

In addition to the generated X.509 certificate, the ECE server certificate (unece.org.cer) will be used in the encryption mechanism (HTTPS) of the message. Depending on your case, you may need to retrieve and store it in your truststore or your application may retrieve it automatically (preferred option).



During the certificate generation process explained in the KeyStore: step by step generation of key pairs section, the email field should be correctly filled as it will be used by the eTIR international system to send email notifications.

8.1.3. Whitelisting servers

The servers of the national customs systems first need to be whitelisted by the ECE IT security team to allow the connection to the servers of the eTIR international system. To do this, the IT experts of the customs authorities need to provide the TIR secretariat with all the IP addresses of the servers of the national customs systems which will send request to the eTIR international system. Similarly, the TIR secretariat stands ready to provide the IP addresses of its servers to perform the same operation on the customs authorities side.



8.2. Endpoint URLs

The list below provides the information about the web service endpoints for the UAT environment as well as the accompanying URLs for the Web Service Description Language (WSDL) files:

UAT web service base URL

https://etir-uat-01.unece.org/etir/v4.3

WSDL for customs authorities

https://etir-uat-01.unece.org/etir/v4.3/customs?wsdl

WSDL for guarantee chains

https://etir-uat-01.unece.org/etir/v4.3/guaranteeChain?wsdl

WSDL for TIR Carnet holders

https://etir-uat-01.unece.org/etir/v4.3/advanceData?wsdl



9. Implementation and test of eTIR messages

9.1. Recommended general approach

9.1.1. Purpose

In this section, the TIR secretariat wishes to share the development processes followed to ensure a timely and qualitative delivery of the eTIR international system, hoping that by doing so, the reader may in turn be able to benefit from our lessons learned.

9.1.2. General approach

The TIR secretariat adopted an Agile approach following the principles of the Agile manifesto. The members of the IT team meet every week to review the work accomplished during the previous week, to discuss about work to be done during the current week and to mention any potential impediment on which other team members could bring their help. To support the work of the TIR secretariat, an internal Knowledge Management System (KMS) features the following components:

- An issue-tracking system which manages all tasks to be done, which offers excellent traceability and accountability;
- A documentation platform which hosts all development, managerial and operational aspects of the eTIR project;
- A source code management system which hosts the code repositories of the TIR information systems.

9.1.3. Continuous Integration

The TIR secretariat also adopted best practices from the DevOps community. In particular, we recognize the important added value of automating as many processes as possible in the software development lifecycle to relieve human beings from mundane tasks, increase reliability by reducing the probability of human errors, and drastically increasing productivity.

In order to have a system as reliable as possible, we deploy regularly our new code through our continuous integration (CI) pipeline. We also rebuild our entire code base every time new code is committed to our code repository, to ensure that at any given time, every completed functionality works as intended.

9.1.4. Extensive testing

We use an automated static code analysis tool to check on a daily basis our source code against sets of rules and best practices created by the IT industry community. This allows to ensure a high quality of the source code, and a continuous training of the members of the IT team.

We also have a target of 70% of our functional code base covered by unit tests, as well as a comprehensive suite of functional non-regression tests written with Apache JMeter. By combining these two types of tests, we ensure that every part of the eTIR international system works as intended, and we protect ourselves from possible regressions when new code is added to our code base.

9.2. Tool kit: list of what we believe is useful

The list below represents the various software that are believed to be useful for the implementation of a client application to the eTIR international system and for which the TIR secretariat has experience with:





- SOAP-UI testing suite: a useful tool for performing ad-hoc tests on SOAP messages (note that you can find in annex the SOAP UI quick guide);
- JMeter testing suite: a useful tool for automating message testing and covering a large scale of scenarios;
- GIT version control system: the industry leading version control system, ensuring that all eTIR international system code and other configuration items are properly versioned;
- IntelliJ IDEA: one of the industry leading Integrated Development Environment (IDE) fitting the eTIR international system technology stack, that proved to enhance our productivity on various aspects;
- SonarQube static code analysis tool: software used for continuous inspection of the code quality that performs automatic reviews with static analysis of the code to detect bugs, so-called "code smells" (which are coding bad practices), and security vulnerabilities.

Kindly note that installing and using these applications is not required. However, those tools have proven to be useful to the TIR secretariat team during the implementation of the eTIR international system.

9.3. SOAP Header generation

The eTIR international system relies on an exchange of web messages using the SOAP protocol v1.2. Beyond the (SOAP) "Action" and (SOAP) "MessageID" elements, as a SOAP extension, WS-Security provides the SOAP header element named "Security", which is designed to act as a container to store all security related information for SOAP request and response messages.

9.3.1. Web service addressing header elements

Among the WS-Addressing Header elements, two of them requires particular attention during the eTIR message implementation.

Action element

The WS-Addressing Header **Action** element is used by the SOAP protocol to indicate the intent of the request. In the context of the eTIR international system, this element is also used to route the request internally and have it processed by the corresponding controller. The "Action" element value is provided in each eTIR message technical guide along with the endpoint URL, following the format **<endpoint namespace>/<Action name>**.



the endpoint URL and endpoint namespace are very similar but for the use of "/" or ":".

MessageID element

The WS-Addressing Header **MessageID** element is used to convey the SOAP protocol message identifier. In the context of the eTIR international system, this element is required as it will be used by the SOAP protocol to identify dependencies between eTIR message (reply, forward, update references). The standard format for this element is composed of an UUID/GUID

("Universally/Globally Unique Identifier") generated value prefixed with "uuid:" as per this format uuid:<UUID/GUID value>



In message examples:

9.3.2. Security element

The section below describes how the **Security** element is defined in the WS-Security schema. The **wsse:Security** header element provides a mechanism for attaching security-related information targeted at a specific recipient in the form of a SOAP actor/role. This element represents the signing steps the message producer took to create the message. This prepending rule ensures that the receiving application can process sub-elements in the order they appear in the **wsse:Security** header element, because there will be no forward dependency among the sub-elements.

Signature element

The Signature element is the root element of an XML Signature

Schema Definition

```
<element name="Signature" type="ds:SignatureType"/>
  <complexType name="SignatureType">
      <sequence>
            <element ref="ds:SignedInfo"/>
            <element ref="ds:SignatureValue"/>
            <element ref="ds:KeyInfo" minOccurs="0"/>
            <element ref="ds:Object" minOccurs="0" maxOccurs="unbounded"/>
            </sequence>
            <attribute name="Id" type="ID" use="optional"/>
            </complexType>
```





In message example:

```
<ds:Signature Id="SIG-AD473EF9595256C9D11540973359402173"
        xmlns:ds="http://www.w3.org/2000/09/xmldsig#">
        <ds:SignedInfo>
         <ds:CanonicalizationMethod Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
            <ec:InclusiveNamespaces PrefixList="SOAP-ENV cus urn"
              xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
         </ds:CanonicalizationMethod>
          <ds:SignatureMethod Algorithm="http://www.w3.org/2000/09/xmldsig#rsa-sha1"/>
          <ds:Reference URI="#id-AD473EF9595256C9D11540973359401172">
            <ds:Transforms>
              <ds:Transform Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
                <ec:InclusiveNamespaces PrefixList="cus urn"
                  xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
              </ds:Transform>
            </ds:Transforms>
           <ds:DigestMethod Algorithm="http://www.w3.org/2000/09/xmldsig#sha1"/>
           <ds:DigestValue>H2Ai····</ds:DigestValue>
         </ds:Reference>
        </ds:SignedInfo>
        <ds:SignatureValue>bY65hsJdkxh40…
        </ds:SignatureValue>
        <ds:KeyInfo Id="KI-AD473EF9595256C9D11540973359401170">
          <wsse:SecurityTokenReference wsu:Id="STR-AD473EF9595256C9D11540973359401171">
           <wsse:KeyIdentifier EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-</pre>
security-1.0#Base64Binary"
                                ValueType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-
profile-1.0#X509v3">
             G9w0BAQsFAAN...
           </wsse:KevIdentifier>
         </wsse:SecurityTokenReference>
       </ds:KeyInfo>
      </ds:Signature>
```

SignatureValue element

The **SignatureValue** element contains the information about the sender's public key which is needed for the eTIR international system to validate the digital signature of the caller. It is always encoded using base64.

Schema Definition

In message example:

```
<ds:SignatureValue>
bY65hsJdkxh40…
</ds:SignatureValue>
```

The **SignatureValue** element contains a signature that only covers the **SignedInfo** element: only the content of this **SignedInfo** element is included into the signature digest.



SignedInfo element

The **SignedInfo** element describes which part of the message was used to generate the signature. It has an attribute **Id** pointing to the SOAP body part of the signed message and we will explain it in more detail in the next element (**Reference**). The structure of the **SignedInfo** element includes the canonicalization algorithm, a signature algorithm, and one or more references. The content of the **SignedInfo** element can be divided into two parts: information about the **SignatureValue** and information about the application content, as we can see in the following XML Schema fragment:

Schema definition:

In message example:

```
<ds:SignedInfo>
 <ds:CanonicalizationMethod Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
   <ec:InclusiveNamespaces PrefixList="SOAP-ENV cus urn"
      xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
 </ds:CanonicalizationMethod>
 <ds:SignatureMethod Algorithm="http://www.w3.org/2000/09/xmldsig#rsa-sha1"/>
  <ds:Reference URI="#id-AD473EF9595256C9D11540973359401172">
   <ds:Transforms>
      <ds:Transform Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
       <ec:InclusiveNamespaces PrefixList="cus urn"
         xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
     </ds:Transform>
   </ds:Transforms>
   <ds:DigestMethod Algorithm="http://www.w3.org/2000/09/xmldsig#sha1"/>
   <ds:DigestValue>H2Ai···</ds:DigestValue>
  </ds:Reference>
</ds:SignedInfo>
```

Canonicalization, or C14N (exclusive XML Canonicalization), is the process of picking one path through all the possible output options, so that sender and receiver can generate the exact same byte intermediate miaht value. no matter what XML software be involved. The SignedInfo/CanonicalizationMethod element specifies how to reconstruct the exact byte stream. The SignedInfo/SignatureMethod element specifies what type of algorithm (e.g., Kerberos or RSA) is used to generate the signature. Together, these two elements describe how to create the digest, and how to protect it from any modification.

In a java based client, this can be configured as following:

```
org.apache.wss4j.dom.message.WSSecSignature wsSecSignature = new WSSecSignature();
//http://www.w3.org/2001/10/xml-exc-c14n#
wsSecSignature.setSigCanonicalization(WSConstants.C14N_EXCL_OMIT_COMMENTS);
//http://www.w3.org/2000/09/xmldsig#rsa-sha1
wsSecSignature.setSignatureAlgorithm(WSConstants.RSA_SHA1);
```

Reference element





The **Reference** element is used to refer to another content. It contains a digest of the content, a description of how that digest was generated (e.g. SHA1), and a specification of how the content should be transformed before the digest is generated. The transformations provide flexibility on how the XML signature is built.

Schema definition:

In message example:

The **DigestMethod** element specifies the hashing algorithm, and the **DigestValue** element is the value of the hash of the content encoded in base64. The key part of the **Reference** element is the set of transforms that may be used. The **Transforms** element is a list of **Transform** elements, each of which specifies a transformation step.

Transforms element

The schema defines an array of transforms, with one XPath element that has a defined structure:

Schema definition:

The content in a Transform element will depend on the Algorithm attribute. For example, if simple XML



is being signed, then there will most likely be a single **Transform** element that specifies a C14N algorithm:

In message example:

```
<ds:Transforms>
<ds:Transform Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
<ec:InclusiveNamespaces PrefixList="cus urn"
xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
</ds:Transform>
</ds:Transforms>
```

KeyInfo element

The last step is to identify the signer, or at least the key that generated the signature (the key that protects the digest from being modified). This task is ensured by the **KeyInfo** element:

Schema definition:

```
<element name="KeyInfo" type="ds:KeyInfoType"/>
<complexType name="KeyInfoType" mixed="true">
    <choice maxOccurs="unbounded">
        <element ref="ds:KeyName"/>
        <element ref="ds:KeyValue"/>
        <element ref="ds:RetrievalMethod"/>
        <element ref="ds:RetrievalMethod"/>
        <element ref="ds:RetrievalMethod"/>
        <element ref="ds:PGPData"/>
        <element ref="ds:SPKIData"/>
        <element ref="ds:SPKIData"/>
        <element ref="ds:MgmtData"/>
        <element ref="lax" namespace="##other"/>
        </choice>
        <attribute name="Id" type="ID" use="optional"/>
</complexType>
```

In message example:

```
<ds:KeyInfo Id="KI-AD473EF9595256C9D11540973359401170">

<wsse:SecurityTokenReference wsu:Id="STR-AD473EF9595256C9D11540973359401171">

<wsse:KeyIdentifier EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-security-

1.0#Base64Binary"

ValueType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile-

1.0#X509v3">

G9w0BAQsFAAN...

</wsse:KeyIdentifier>

</wsse:KeyIdentifier>

</wsse:SecurityTokenReference>

</ds:KeyInfo>
```

SecurityTokenReference element

The digital signature operation requires a key be specified. The element containing the key in question may be located elsewhere in the message or completely outside the message. The **SecurityTokenReference** element provides a mechanism for referencing security tokens and other key bearing elements. The **SecurityTokenReference** element provides an open content model for referencing key bearing elements. In order to ensure a consistent processing model across all the token types supported by WSS: SOAP Message Security, the **SecurityTokenReference** element shall be used to specify all references to X.509 token types in signature or encryption elements that comply with this profile (complete information related to this element can be found on the Oasis website dedicated page).





A SecurityTokenReference element may reference an X.509 token type by one of the following means:

- Reference to a subject Keyldentifier: the SecurityTokenReference element contains a Keyldentifier element that specifies the token data by means of a X.509 Subject Key Identifier reference. A subject key identifier may only be used to reference an X.509v3 certificate.
- Reference to a **BinarySecurityToken**: the **SecurityTokenReference** element contains a **Reference** element that references a local **BinarySecurityToken** element or a remote data source that contains the token data itself.
- Reference to an Issuer and SerialNumber: the SecurityTokenReference element contains a X509Data element that contains a X509IssuerSerial element that uniquely identifies an end entity certificate by its X.509 Issuer and Serial Number.

In message example (using a reference to a key identifier):

```
<ds:KeyInfo Id="KI-AD473EF9595256C9D11540973359401170">

<wsse:SecurityTokenReference wsu:Id="STR-AD473EF9595256C9D11540973359401171">

<wsse:KeyIdentifier EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-security-

1.0#Base64Binary"

ValueType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile-

1.0#X509v3">

G9w0BAQsFAAN...

</wsse:KeyIdentifier>

</wsse:SecurityTokenReference>

</ds:KeyInfo>
```

For example, the following configuration will set the **Keyldentifier** element instead of using a **X509Data** element:

```
org.apache.wss4j.dom.message.WSSecSignature wsSecSignature = new WSSecSignature();
wsSecSignature.setKeyIdentifierType(WSConstants.X509_KEY_IDENTIFIER);
```

Keyldentifier element

A token should be referenced using a **Keyldentifier** element. The following table list both encoding and value types.

URI Fragment	URL
#Base64Binary	http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-security-1.0#Base64Binary
#X509v3	http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile-1.0#X509v3

In message example:

```
<ds:KeyInfo Id="KI-AD473EF9595256C9D11540973359401170">

<wsse:SecurityTokenReference wsu:Id="STR-AD473EF9595256C9D11540973359401171">

<wsse:KeyIdentifier EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-security-

1.0#Base64Binary"

ValueType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile-

1.0#X509v3">

G9w0BAQsFAAN...

</wsse:KeyIdentifier>

</wsse:SecurityTokenReference>

</ds:KeyInfo>
```

X509Data element



Schema definition:

```
<complexType name="X509IssuerSerialType">
<sequence>
<element name="X509IssuerName" type="string"/>
<element name="X509SerialNumber" type="integer"/>
</sequence>
</complexType>
```

X.509 certificates are supported through the **ds:X509Data** element. This element allows the signer to embed its certificate (encoded in Base64), or any other alternative methods to verify the certificate: a subject's name, the issuer's name and serial number, the key identifier, or another format. The signer can also include a current copy of the Certificate Revocation List (CRL), to show that the signer's identity was valid at the time the document was signed.





9.3.3. SOAP eTIR message example

```
<?xml version="1.0" encoding="UTF-8"?>
<soap:Envelope xmlns:soap="http://www.w3.org/2003/05/soap-envelope" xmlns:cus="etir:v4.3:customs" xmlns:etir=</pre>
"etir:I5:v4.3">
  <soap:Header xmlns:wsa="http://www.w3.org/2005/08/addressing">
    <wsse:Security xmlns:wsse="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssecurity-secext-1.0.xsd"</pre>
      xmlns:wsu="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssecurity-utility-1.0.xsd">
      <ds:Signature Id="SIG-AD473EF9595256C9D11540973359402173"</pre>
        xmlns:ds="http://www.w3.org/2000/09/xmldsig#">
        <ds:SignedInfo>
          <ds:CanonicalizationMethod Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
            <ec:InclusiveNamespaces PrefixList="soap wsa cus etir"
              xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
          </ds:CanonicalizationMethod>
          <ds:SignatureMethod Algorithm="http://www.w3.org/2000/09/xmldsig#rsa-sha1"/>
          <ds:Reference URI="#id-AD473EF9595256C9D11540973359401172">
            <ds:Transforms>
              <ds:Transform Algorithm="http://www.w3.org/2001/10/xml-exc-c14n#">
                <ec:InclusiveNamespaces PrefixList="cus etir"
                  xmlns:ec="http://www.w3.org/2001/10/xml-exc-c14n#"/>
              </ds:Transform>
            </ds:Transforms>
            <ds:DigestMethod Algorithm="http://www.w3.org/2000/09/xmldsig#sha1"/>
            <ds:DigestValue>H2Ai···</ds:DigestValue>
          </ds:Reference>
        </ds:SignedInfo>
        <ds:SignatureValue>bY65hsJdkxh40…
        </ds:SignatureValue>
        <ds:KeyInfo Id="KI-AD473EF9595256C9D11540973359401170">
          <wsse:SecurityTokenReference wsu:Id="STR-AD473EF9595256C9D11540973359401171">
            <wsse:KeyIdentifier EncodingType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-soap-message-</pre>
security-1.0#Base64Binary" ValueType="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-x509-token-profile-
1.0#X509v3">
              G9w0BAQsFAAN...
            </wsse:KeyIdentifier>
          </wsse:SecurityTokenReference>
        </ds:KeyInfo>
      </ds:Signature>
    </wsse:Security>
    <wsa:Action>etir:v4.3:customs/queryGuarantee</wsa:Action>
    <wsa:MessageID>uuid:8a20af11-8170-495d-9563-6a89b32ef745</wsa:MessageID>
 </soap:Header>
  <soap:Body xmlns:wsu="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssecurity-utility-1.0.xsd" wsu:Id=
"id-942cd702-1de3-4f27-bfcd-6628ab5d3143">
    <cus:queryGuarantee>
      <etir:InterGov>
        <etir:FunctionCode>9</etir:FunctionCode>
        <etir:ID>656dbce8-e810-44ec-8f3d-5f8a9b425d99</etir:ID>
        <etir:TypeCode>I5</etir:TypeCode>
        <etir:ReplyTypeCode>00</etir:ReplyTypeCode>
        <etir:ObligationGuarantee>
          <etir:ReferenceID>XC95xxxxx</etir:ReferenceID>
        </etir:ObligationGuarantee>
      </etir:InterGov>
    </cus:queryGuarantee>
  </soap:Body>
</soap:Envelope>
```



9.4. Implementation of MetaData fields

For each message, an XML envelope represented by the **DocumentMetadata** element will be used to encapsulate the required metadata as well as the eTIR message itself. Within the **DocumentMetadata** envelope, the metadata are defined by the following elements:

9.4.1. Field details

eTIR field name	Mapping to the XML element (XPath)	Status	Cardinality	Format	Code lists	Conditions	Rules
⊢ Responsible agency, coded	ResponsibleAgencyCode	11	R	an2	CL28		
\vdash Specifications name, coded	AgencyAssignedCustomizationCode	11	R	an6	CL29		
dash Specifications version, coded	AgencyAssignedCustomizationVersionCode	11	R	an3	CL30		
├── Communication MetaData	CommunicationMetaData	R	11				
$ $ \vdash Preparation date and time	CommunicationMetaData/PreparationDateTime	0	01	an35			
	CommunicationMetaData/Recipient	R	11				
└ Identifier	CommunicationMetaData/Recipient/ID	R	11	an35			
└── Sender	CommunicationMetaData/Sender	R	11				
└ Identifier	CommunicationMetaData/Sender/ID	R	11	an35			

9.4.2. Field descriptions & usages

eTIR field name	Mapping to the XML element (XPath)	Description	Usage
⊢ Responsible agency, coded	ResponsibleAgencyCode	Code of the agency controlling the specifications of the message	The value should be the code "AJ" (UN/ECE/TRANS) representing the agency responsible for the eTIR specifications from the list Controlling agency (UN/EDIFACT 0051)
⊢ Specifications name, coded	AgencyAssignedCustomizationCode	Code of the name of the specifications of the message	The value should be the code "1" (eTIR) representing the name of the specifications followed by this message from the list Specifications name (eTIR)
⊢ Specifications version, coded	AgencyAssignedCustomizationVersionCode	Code of the version of the specifications of the message	The value should be the code representing the version of the specifications followed by this message from the list Specifications version (eTIR)
├── Communication MetaData	CommunicationMetaData	Class giving additional information on the metadata of the message	





eTIR field name	Mapping to the XML element (XPath)	Description	Usage
⊣ Preparation date and time	CommunicationMetaData/PreparationDateTime	Date and time when the message has been prepared by the sender	The value should be a date and time to be provided following the EDIFACT 208 format CCYYMMDDHHMMSSZHHMM. For Example: 20200820145600+0100 represents 20 August 2020 at 14:56 UTC+01:00.
	CommunicationMetaData/Recipient	Class giving additional information on the recipient of the message	
└ Identifier	CommunicationMetaData/Recipient/ID	Unique identifier of the recipient of the message	The value should be the unique identifier of the eTIR stakeholder to whom to the message is sent
└─┬ Sender	CommunicationMetaData/Sender	Class giving additional information on the sender of the message	
└ Identifier	CommunicationMetaData/Sender/ID	Unique identifier of the sender of the message	The value should be the unique identifier of the eTIR stakeholder who sent the message



Additional information can be found on this aspect in section IV.C.3.(a) of the eTIR technical specifications.

9.5. Implementation of the numerical fields

The eTIR messages feature several attributes that should contain numerical values. Here is the list of specifications that are required for this type of attributes:

- All numeric attributes are either a cardinal value (positive integer value) or a decimal value;
- The decimal separator is the decimal point "." and no other symbols are permitted as decimal separator;
- Thousands separators, such as a comma or a space character, shall not be used;
- · Signs, whether positive or negative, shall not be used (all values are intrinsically positive);
- · For numerical values, leading and trailing zeroes shall not be used;
- If the decimal point is present, at least one digit shall be present before the decimal point;
- If the decimal point is present, at least one digit shall be present after the decimal point.

The table below shows the results of the validation mechanism applied to several examples of numerical values that follow the data type "n..16,6" which describes a decimal number with a total number of digits of eleven maximum and a decimal part of three digits maximum.

	Value	Validation result	Reason for the result of the validation
ľ	1234567890.123456	Valid	
	12345678901.123456	Invalid	Too many digits in total
	1234567.1234567	Invalid	Too many digits after the decimal point
	0123	Invalid	Leading zeros are not allowed
	+123	Invalid	The plus sign is not allowed
	-123	Invalid	The minus sign is not allowed
	1,234	Invalid	Thousands separators are not allowed
	.3	Invalid	A digit is missing before the decimal point
	12345.	Invalid	A digit is missing after the decimal point
	0.3	Valid	
	1.3E1	Invalid	Only digits and the decimal point are allowed
	1234567890123456	Valid	The type "n16,6" can have maximally 16 digits

Additional information can be found on this aspect in section IV.C.3.(b) of the eTIR technical specifications.

9.6. Implementation of the text fields

The eTIR messages feature attributes that should contain free text values (that are not codes or identifiers). Here is the list of specifications that are required for this type of attributes:

- All text attributes' values are case sensitive (i.e. uppercase and lowercase letters are treated as distinct);
- Leading and trailing spaces (both normal spaces and non-breaking spaces) shall not be used within text attributes. If it's the case, they will be trimmed;
- It is recommended for all XML elements representing eTIR text attributes to also feature an optional XML attribute named "languageID" whose value represents the language used for the value of eTIR text attribute. The value of the XML attribute "languageID" is the code of the





language from code list 20 (Language name - ISO 639-1). In case this XML attribute is omitted, the text is considered to be in English.

Certain characters cannot be used in XML messages because they have a special meaning. Using these characters can cause the parser to misinterpret the resulting data. The solution is to replace the characters by other expressions so that the parser can interpret them correctly as data, and not confuse them for XML markup. The following table lists all these substitutions.

Character	Expression to be used instead
& (ampersand)	&
> (greater-than character)	>
" (straight double quotation mark)	n
' (straight single quotation mark)	,

Additional information can be found on this aspect in section IV.C.3.(c) of the eTIR technical specifications.

9.7. Implementation of coded fields

The eTIR messages feature attributes that should contain codes from given code lists. Codes are alphanumerical values and are, therefore, considered as text (and not numerical values). Here is the list of specifications that are required for this type of attributes:

- All coded attributes should feature a code that belongs to the code list to which the attribute is bound;
- If restricted codes are specified for a given coded attribute in the eTIR specifications (functional or technical), then the value of this attribute should only be one of these restricted codes.

9.8. Implementation of the date fields

The eTIR messages contain several fields in which dates have to be entered. For some of these fields, the format only includes a date and for some others, it also includes the time. This section explains more in detail how to properly populate these fields.

9.8.1. Fields with dates only

In the XML Schema Definition (XSD) files, this type is named **EtirDateType** and is defined as follows, along with the types it inherits from.



EtirDateType definition

```
<xs:complexType name="EtirDateType">
      <xs:simpleContent>
            <xs:extension base="ds:DateTimeType_102_S">
                  <xs:attribute name="formatCode" use="optional">
                         <xs:simpleType>
                              <xs:restriction base="xs:string">
                                     <xs:enumeration value="102"/>
                               </xs:restriction>
                         </rs:simpleType>
                  </xs:attribute>
            </xs:extension>
     </xs:simpleContent>
</rs:complexType>
<xs:simpleType name="DateTimeType_102_S">
      <xs:restriction base="ds:DateTimeType_S">
            <xs:pattern value="[1-9][0-9][0-9][0-9](([0][1|3|5|7|8])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][1-9]|[1-2][0-1])|([0][4|6|9])([0][4|6|9])([0][4|6|9])([0][4|6|9])([0][4|6|9])([0][4|6|1])|([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][4|6|1])([0][
9][3][0]))"/>
    </xs:restriction>
</xs:simpleType>
<xs:simpleType name="DateTimeType_S">
     <xs:restriction base="xs:string">
            <xs:pattern value=".{1,35}"/>
      </xs:restriction>
</xs:simpleType>
```

The format of this type of date is aligned on the UN/EDIFACT format code 102: CCYYMMDD

With:

- · CCYY: the year on four digits. Examples: 1979, 2020;
- MM: the month on two digits from 01 to 12 starting with 01 for January;
- DD: the day of the month on two digits from 01 to 31.

Samples:

- 01 January 1970 is coded as "19700101";
- 29 February 2020 is coded as "20200229";
- 31 December 2045 is coded as "20451231".

The date field also contains an optional attribute named **formatCode** which value is therefore always "102". With this format, there is no notion of time zone and the date has to be regarded as valid in all time zones.

The following XML code show a sample date only field.

Expiration of a guarantee on 01 August 2024

<ExpirationDateTime formatCode="102">20240801</ExpirationDateTime>

Additional information can be found on this aspect in section IV.C.3.(e) of the eTIR technical specifications.





9.8.2. Fields with dates and time

In the XML Schema Definition (XSD) files, this type is named **EtirDateTimeType** and is defined as follows, along with the types it inherits from.

EtirDateTimeType definition

```
<xs:complexType name="EtirDateTimeType">
      <xs:simpleContent>
            <xs:extension base="ds:DateTimeType_208_S">
                  <xs:attribute name="formatCode" use="optional">
                        <xs:simpleType>
                             <xs:restriction base="xs:string">
                                    <xs:enumeration value="208"/>
                              </xs:restriction>
                        </xs:simpleType>
                  </xs:attribute>
            </xs:extension>
     </xs:simpleContent>
</rs:complexType>
<xs:simpleType name="DateTimeType_208_S">
     <xs:restriction base="ds:DateTimeType_S">
            <xs:pattern value="[1-9][0-9][0-9][0-9](([0][1|3|5|7|8])([0][1-9]|[1-2][0-9]|[3][0-1])|([0][4|6|9])([0][1-9]|[1-
2][0-9]|[3][0])|([0][2])([0][1-9]|[1-2][0-9])|([1][0|2])([0][1-9]|[1-2][0-9]|[3][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([0][1-9]|[1-2][0-1])|([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1][1])([1
9][3][0]))(([0-1][0-9])(2[0-3]))[0-5][0-9](([0-5][0-9]|60))[\-+]((0[0-9])(1[0-4]))[0-5][0-9]"/>
     </xs:restriction>
</xs:simpleType>
<xs:simpleType name="DateTimeType_S">
     <xs:restriction base="xs:string">
            <xs:pattern value=".{1,35}"/>
      </xs:restriction>
</xs:simpleType>
```

The format of this type of date and time is aligned on the UN/EDIFACT format code 208: CCYYMMDDHHMMSSZHHMM

With, defined sequentially:

- CCYY: the year on four digits. Examples: 1979, 2020;
- MM: the month on two digits from 01 to 12 starting with 01 for January;
- DD: the day of the month on two digits from 01 to 31;
- HH: the hour of the day on two digits from 00 (for midnight) to 23 (for eleven PM);
- MM: the minutes of the day on two digits from 00 to 59;
- SS: the seconds of the day on two digits from 00 to 59. 60 is also allowed in the case of a leap second;
- Z: the introduction of the time zone with either a " or a '-'. If the time zone has no offset, either '-' or " can be used;
- HH: the hours of the offset of the time zone from 01 to 14;
- MM: the minutes of the offset of the time zone from 00 to 59.

Samples:

- 01 January 1970 00:00:00 in London (Time offset: +00:00) is coded as "19700101000000+0000";
- 29 February 2020 09:45 UTC+4 in New York (Time offset: -05:00) is coded as "20200229094536-0500";



• 31 December 2045 22:06:59 in South Tarawa, Kiribati (Time offset: +14:00) is coded as "20451231220659+1400".

The date and time field also contains an optional attribute named **formatCode** which value is therefore always "208".

The following XML code show a sample date and time field.

Acceptance of a guarantee on 01 July 2021 10:03:42 in Istanbul (Time offset +03:00)

<AcceptanceDateTime formatCode="208">20210701100342+0300</AcceptanceDateTime>

Additional information can be found on this aspect in section IV.C.3.(f) of the eTIR technical specifications.

9.9. Implementation of the Message Identifier / Original Message Identifier

9.9.1. General

All messages sent and received are uniquely identified using the **Message Identifier** field. This field must be set by the Sender in the request message. The Receiver will set another unique value for the **Message Identifier** field of the response message. In addition to that, the Receiver will also set the **Original Message Identifier** field of the response message with the value of the **Message Identifier** field of the response message with the value of the **Message Identifier** field of the response message with the value of the **Message Identifier** field of the response message with the value of the **Message Identifier** field of the response message. This method allows a full traceability of the Request/Response messages.

Additional information can be found on this aspect in section IV.C.3.(g) of the eTIR technical specifications.

9.9.2. Request message

The Receiver must set the **Message Identifier** field of the message using the following format:

UUID

Where:

• UUID: a universally unique identifier v4 as detailed in RFC 4122. Version 4 is based on pseudorandom numbers hence the need to keep the SenderID to decrease the probabilities of collisions between messages sent by various eTIR stakeholders.

The main programming languages provide native helper classes to generate a UUID v4:

In Java:

java.util.UUID.randomUUID();

In C#:

System.Guid.NewGuid();

Here are some samples of valid values for the Message Identifier field:





Sample 1:

<urn:ID>6aca5f82-2285-4f00-b4ae-36269d4cc865</urn:ID>

9.9.3. Response message

The Receiver receives the request message from the Sender and stores the value of the **Message Identifier** field. When preparing the response message, the Receiver will set a new value for the **Message Identifier** field of that message following the same way as described in the section above. Then the stored value of the **Message Identifier** field of the request message will be set to the **Original Message Identifier** of the response message being prepared.

9.10. Implementation of the Sequence number attributes

"Sequence number" attributes are sometimes used in classes that are represented as lists in the eTIR messages. These attributes are needed to express a specific sequence between the elements of these lists. For example, the "Sequence number" attribute in the "TransportMeans" class is used to determine the order of the means by which the goods will be transported.

Here is the list of specifications that have to be applied to the "Sequence number" attributes, knowing that they represent the 1-based index65 of the parent class in the list:

- The value of this attribute should always be superior or equal to 1;
- The value of this attribute is unique in the same sequence;
- Except when otherwise specified by the description of the field or by rules, the values of the "Sequence number" attributes of the same list should start with 1 and should be incremented without leaving any gap in the sequence.

Additional information can be found on this aspect in section IV.C.3.(h) of the eTIR technical specifications.

9.11. Implementation of the Measurement sub-attributes

Several attributes are used to contain measurement values: "Total gross weight", "Gross weight" and "Size". These eTIR attributes also feature a required XML attribute named "unitCode" which value represents the unit used for the measurement value. The value of the XML attribute "unitCode" is the code of the measurement unit from code list 21 (Measurement unit – UNECE Recommendation 20).

The possible codes used for the "Size" attribute belonging to the "BinaryFile" class are restricted to the following:

- AD: byte;
- 2P. kilobytes;
- 4L: megabytes.

It is recommended to use the following codes for the "Total gross weight" and "Gross weight" attributes:

- GRM: gram;
- KGM: kilogram;
- DTN: decitonne (quintal);
- TNE: tonne (metric ton).



Additional information can be found on this aspect in section IV.C.3.(i) of the eTIR technical specifications.

9.12. Validation mechanism

When the eTIR international system receives and processes a message, it first performs a series of validations on the message itself, in the context of the related guarantee, holder or transport. The following layers of validation are applied to ensure the correctness of the message, its alignment with the specifications and its pertinence:

- A layer validating the structure and the values of the message, capturing all errors found and returning them as a list in the response message. Values of attributes which are bound to code lists are also checked against the possible values of the current versions of the relevant code lists: any value out of the code lists (or the list of restricted codes, if applicable) would raise an error. All these errors are part of the first family of errors (1XX – Validation);
- A generic layer validating the message as a whole, using the XSD file defining the type of message. Potential errors detected are also part of the first family of errors (1XX – Validation);
- Then, the message starts to be processed by the eTIR international system. If any inconsistency is detected in the sequence of the messages or with the records of the eTIR database, additional errors may be returned and, in this case, the first error found is immediately returned. At this stage, errors can belong to the second and third families of errors (2XX – Workflow and 3XX – Functional);
- Finally, a last layer of validation is performed at the eTIR database level, where its set of integrity constraints can reject the recording of the values of the message when they do not match the constraints. In theory, this last safety net should never be catching any issues as they should have been detected and returned by the previous validation layers. If such a rejection occurs, an error from the fourth family will be raised (4XX Internal) and the eTIR stakeholder who receives such error should contact the eTIR service desk as soon as possible to report it.

Additional information can be found on this aspect in sections III.C.6 and IV.C.4 of the eTIR technical specifications.

9.13. Error management

9.13.1. Introduction to error management

When the eTIR international system receives and processes a message, it performs a series of validations on the message itself and issues a response to the system which has sent this message. If anything goes wrong during these validation and processing steps, a list of errors is returned in the response message. The minimal requirement is to report the first error detected. All other detected errors should be reported, if possible. Each of these errors is presented as an **Error code** with a list of **Pointers** which can be used to point to a specific XML element of the message using the XPath syntax. The list of all the error codes is available on the Error code (eTIR) page.

Additional information can be found on this aspect in sections III.C.6 and IV.C.5 of the eTIR technical specifications.

9.13.2. Presentation of error codes

The list of error codes (code list 99) is specific to eTIR as it allows IT teams to better understand errors, especially while implementing the interconnection of their information systems to the eTIR international system. This should result in an overall faster implementation and in more accurate processing of the errors from the system sending messages to the eTIR international system. Furthermore, a detailed error code system also greatly simplifies the communication between the eTIR





stakeholders and the eTIR service desk, in case of an incident, to identify and resolve the underlying problem. The list of error codes is based on the best practices from the IT industry. Like the list of HTTP status codes, all error codes have three digits, and the first digit of the status code defines the type of error:

- 1XX Validation: validation of the message and if its fields;
- 2XX Workflow: workflow related problems;
- · 3XX Functional: other functional problems;
- 4XX Internal: eTIR international system internal problems;
- 5XX Customs:: errors raised by customs authorities.

Each type of error has a default error code which indicates, at least, the type of the error if the system cannot send a more explicit error.

9.13.3. Sample errors

Below is an example of how a single error is returned:

Missing required element

```
<ns4:Error>
<ns4:ValidationCode>101</ns4:ValidationCode>
<ns4:Pointer>
<ns4:SequenceNumeric>1</ns4:SequenceNumeric>
<ns4:Location>/DocumentMetadata/InterGov/ObligationGuarantee/ReferenceID</ns4:Location>
</ns4:Pointer>
</ns4:Error>
```

In the above example, the **ValidationCode** XML element is set to the error code and the Location XML element inside the Pointer XML element points towards the problematic element of the request message using the XPath syntax.

When multiple errors with the same error code are returned, they should be aggregated in a single Error XML element, with a list of Pointer XML elements, as shown in this second XML example in the figure below.

Example of missing multiple required element

```
<ns4:Error>
<ns4:ValidationCode>101</ns4:ValidationCode>
<ns4:Pointer>
<ns4:SequenceNumeric>1</ns4:SequenceNumeric>
<ns4:Location>/DocumentMetadata/InterGov/ObligationGuarantee/ReferenceID</ns4:Location>
</ns4:Pointer>
<ns4:Pointer>
<ns4:SequenceNumeric>2</ns4:SequenceNumeric>
<ns4:Location>/DocumentMetadata/InterGov/ObligationGuarantee/Surety/ID</ns4:Location>
</ns4:Pointer>
</ns4:Pointer>
</ns4:Pointer>
```

Finally as an example, please find below a complete response to an **I1** - **Accept guarantee** message containing multiple errors:



Example of a complete I2 - Acceptance results message body with multiple errors returned



9.13.4. Error handling

Each national customs systems which interconnects with the eTIR international system needs to properly handle the errors returned in the response message. When implementing the various pairs of eTIR messages, developers will find it convenient to refer to the eTIR error codes page, especially to the 'Observations' column in the tables, to see which error codes could be raised. When receiving messages from the eTIR international system, errors should be handled in such a way that the relevant information is transmitted to the relevant national customs systems. As all errors are critical and mean a failure to process the message, the appropriate follow-up actions should be performed by the users of the national customs system.

The same goes for the national customs systems which may send back errors to the eTIR international system when receiving requests that they cannot process (this might be the case for the following pairs of messages: I15/I16, E9/E10, E11/E12 and E13/E14). The national customs systems should follow the same specifications as detailed above when errors have to be reported to the eTIR international system when sending response messages.





10. Fallback procedures

eTIR functional fallback procedures are currently described in the Approved amendments to the eTIR conceptual, functional and technical documentation - v.4.2a that will be included in the next version of the eTIR specification (v4.3). Moreover, each message may have a technical fallback procedure that will be described in the corresponding eTIR message implementation guides.

11. Support and contact

Kindly note that in the context of the interconnections projects by customs, the eTIR service desk stands ready to assist contracting parties while interconnecting their national customs systems to the eTIR international system. Also, in case of questions or issues related to this document or to the eTIR international system, you can use the contact details below (contacts by email should be preferred).

Organization United Nations Economic Commission For Europe TIR secretariat Palais des Nations, 1211 Geneva 10, Switzerland

Contact Email: etir@un.org Phone: +41 (0)22 917 55 06



12. Annexes

12.1. Version history

Date	Author	Version	Notes	eTIR specification version reference
28/07/2020	TIR secretariat	1.0	Initial draft	4.3a
08/10/2020	TIR secretariat	1.1	Updated part related to security and wording simplification	4.3a
27/11/2020	TIR secretariat	1.2	Added additional information related to SecurityTokenReference element	4.3a
07/09/2021	TIR secretariat	1.3	Aligned the contents of the document with the eTIR technical specifications v4.3 presented at WP.30/GE.1 in September 2021. Added message metadata documentation and updated URLs to point to new eTIR documentation portal	4.3.0
22/09/2021	TIR secretariat	1.3.1	Added a solution to work around an issue with XSD/WSDL v4.3.6	4.3.0



12.2. Glossary

API

An Application Programming Interface (API) is a software interface which is used for accessing an application or a service from a program.

Asymmetric encryption algorithm

A cryptographic system that uses two keys: a public key known to everyone and a private (or secret) key only known by the owner of the key pair. For example, when Alice wants to send a secured message to Bob, she uses Bob's public key to encrypt the message. Bob then uses his private key to decrypt it. RSA is an example of asymmetric algorithm.

Authentication

The process of verifying or testing that the claimed identity is valid is authentication. Authentication requires the subject to provide additional information that corresponds to the identity they are claiming. The most common form of authentication is using a password (this includes the password variations of personal identification numbers (PINs) and passphrases). Authentication verifies the identity of the subject by comparing one or more factors against the database of valid identities (that is, user accounts).

B2B

Business to Business relationship (where business refers to the private sector).

B2C

Business to Customs relationship (where business refers to the private sector).

C2B

Customs to Business relationship (where business refers to the private sector).

C2C

Customs to Customs relationship.

Certification Authority (CA)

A certification authority, or CA, holds a trusted position because the certificate that it issues binds the identity of a person or business to the public and private key pair (asymmetric cryptography) that are used to secure most internet transactions. For example, when a business or person wants to use these technologies, they request to a CA to issue them a certificate. The CA collects information about the person or business that it will certify before issuing the certificate.

Confidentiality

Confidentiality is the concept of the measures used to ensure the protection of the secrecy of data, objects, or resources. The goal of confidentiality protection is to prevent or minimize unauthorized access to data. Confidentiality focuses security measures on ensuring that no one other than the intended recipient of a message receives it or is able to read it. Confidentiality protection provides a means for authorized users to access and interact with resources, but it actively prevents unauthorized users from doing so.

Digital Signature

A digital code that can be attached to an electronically transmitted message that two distinct goals: 1) Digitally signed messages assure the recipient that the message truly came from the claimed sender. They enforce non-repudiation (that is, they preclude the sender from later claiming that the message is a forgery) and 2) Digitally signed messages assure the recipient that the message was not altered while in transit between the sender and recipient. This protects against both malicious modification (a third party altering the meaning of the message) and unintentional modification (because of faults in the communications process, such as electrical interference).



Environments

Software is developed and maintained on several environments: the Development environment is used for implementing the piece of software, the User Acceptance Test environment is used to test and validate it with other stakeholders and the Production environment is used to exploit the system when it is "live", available as a service to its end users.

Error

An error is a severe validation failure, which will cause the message to be rejected.

eTIR IS

Acronym occasionally used in diagrams to refer to the eTIR international system.

eTIR stakeholder

An entity being part of the eTIR system and using the eTIR procedure as described in the Annex 11 of the TIR Convention. An eTIR stakeholder uses its information systems to be part of the eTIR system and can be any of the following entities:

- UNECE with the eTIR international system;
- IRU, representing the guarantee chain, with their information systems;
- · customs authorities with their national customs systems;
- · Holders with their information systems.

Hash

A hash value (or simply hash), also called a message digest, is a value generated from a text. The hash is substantially smaller than the text itself, and is generated by a formula in such a way that it is extremely unlikely that some other text will produce the same hash value.

Integrity

Integrity is the concept of protecting the reliability and correctness of data. Integrity protection prevents unauthorized alterations of data. It ensures that data remains correct, unaltered, and preserved. Properly implemented integrity protection provides a means for authorized changes while protecting against intended and malicious unauthorized activities (such as viruses and intrusions) as well as mistakes made by authorized users (such as mistakes or oversights).

ITDB

The International TIR DataBank is a UNECE application custodian of all TIR Carnet holder and customs office data. The data in this information system is maintained by the national associations and customs authorities of the TIR system.

Keystore

A keystore is a database of keys and is used to store certificates, including the certificates of all trusted parties, for use by a program. Through its keystore, an entity, can authenticate other parties, as well as authenticate itself to other parties.

Non-repudiation

Non-repudiation ensures that the subject of an activity or who caused an event cannot deny that the event occurred. Non-repudiation prevents a subject from claiming not to have sent a message, not to have performed an action, or not to have been the cause of an event. It is made possible through identification, authentication, authorization, accountability, and auditing. Non-repudiation can be established using digital certificates, session identifiers, transaction logs, and numerous other transactional and access control mechanisms.





OASIS

Organization for the Advancement of Structured Information Standards (OASIS) is a non-profit, international consortium whose goal is to promote the adoption of product-independent standards.

PKI

Public-Key Infrastructure (PKI) is the infrastructure needed to support asymmetric cryptography.

Receiver

In the context of this document and of all the documents related to the message pairs, the "receiver" is the information system of the eTIR stakeholder which receives a message sent by another eTIR message and processes it.

RSA

The RSA algorithm was invented by Ronald L. Rivest, Adi Shamir, and Leonard Adleman in 1977. It is an asymmetric algorithm, that is to say it uses two different keys with a mathematic relationship to each other. The public key and private keys are carefully generated using the RSA algorithm; they can be used to encrypt information or sign it.

Sender

In the context of this document and of all the documents related to the message pairs, the "sender" is the information system of the eTIR stakeholder which prepares and sends an eTIR message to another eTIR stakeholder.

SOAP

Simple Object Access Protocol (SOAP) is a messaging protocol specification for exchanging information in the implementation of web services. It is an XML-based protocol consisting of three parts:

- an envelope, which defines the message structure (a header and a body) and how to process it;
- a set of encoding rules for expressing instances of application-defined datatypes;
- · a convention for representing procedure calls and responses.

Token

A token (sometimes called a security token) is an object that controls access to a digital asset. Traditionally, this term has been used to describe a hardware authenticator, a small device used in a networked environment, to create a one-time password that the owner enters into a login screen along with an ID and a PIN. However, in the context of web services and with the emerging need for devices and processes to authenticate to each other over open networks, the term token has been expanded to include software mechanisms too. A token may be an X.509 certificate, that associates an identity to a public key for example.

Truststore

A truststore is a KeyStore file that contains certificates from other parties that you expect to communicate with, or from Certificate Authorities that you trust to identify other parties.

Web service

The definition of a web service is a communication over a network between two applications (not between a person and an application for example). Machine-to-machine is another term to define this type of communication.

Web Services Security (WS-Security)

The Web Services Security (WS-Security) specification describes enhancements to SOAP 1.1 that increase the protection (integrity) and confidentiality of the messages. These enhancements include functionality to secure SOAP messages through XML digital signature, confidentiality



through XML encryption, and credential propagation through security tokens (e.g. X.509 token).

WSDL

Web Service Description Language (WSDL) is an XML-based interface description language that is used for describing the functionality offered by a web service.

X.509 digital certificate

In general use, a certificate is a document issued by some authority to attest to a truth or to offer certain evidence. A digital certificate is commonly used to offer evidence in electronic form about the holder of the certificate. In PKI it comes from a trusted third party, called a Certification Authority (CA) and it bears the digital signature of that authority.

X.509 token

The X.509 token is the X.509 certificate with the end user's credentials that can be passed in the SOAP message. The X.509 token can be used to authenticate the user based on the trust relationship (PKI). The X.509 token is also used to sign, encrypt and decrypt the SOAP message.

XML

XML stands for eXtensible Markup Language which is a language that defines a set of rules for encoding documents in a format that is both human-readable and machine-readable. It is used by SOAP to encode messages sent by web services.

XML Signature

The XML Signature specification is a joint effort between W3C and IETF. XML Signatures provide integrity, message authentication and/or signer authentication services any type for data, whether located within the XML that includes the signature or elsewhere.

XSD

XSD (XML Schema Definition) is a World Wide Web Consortium (W3C) recommendation that specifies how to formally describe the elements in an Extensible Markup Language (XML) document.





12.3. Technical summary

This annex lists all technical information in one page for ease of reference.

Кеу	Value	Comments
eTIR Specifications	4.3.0	
URL of the UAT environment n°1	https://etir-uat-01.unece.org	
URL of the UAT environment n°2	https://etir-uat-02.unece.org	
SOAP endpoint for Internal messages coming from national customs systems	{environment URL}/etir/v4.3/customs	
SOAP endpoint for External messages coming from guarantee chain systems	{environment URL}/etir/v4.3/guaranteeChain	
SOAP endpoint for External messages coming from TIR Carnet holder information systems	{environment URL}/etir/v4.3/advanceData	
Version of the SOAP protocol	v1.2	
Protocol used for HTTPS	TLS v1.2 and v1.3	It is recommended to ensure that your information system can use TLS v1.3 as TLS v1.2 will likely to be decommissioned for security reasons in 2021.
Version of the X.509 certificate	3	These are the X.509 certificates used as electronic signatures to sign the messages sent between the various of the eTIR system
Size of the key for the generation of the X.509 certificate	4096 bits	
Signature algorithm for the generation of the X.509 certificate	e SHA-256 with RSA	
Version of UUID to use	4	UUIDs are used in the Message Identifier and Functional Reference fields



12.4. KeyStore: step by step generation of key pairs

12.4.1. Using the KeyStore Explorer application

This procedure describes keystore manipulations using the open-source GUI tool KeyStore Explorer. The latest version of the KeyStore Explorer is available for download on this page: http://www.keystore-explorer.org/

Key pair generation

1. Open KeyStore Explorer, click create a new KeyStore button and choose JKS as a type

	n = 0 1	
Key	Store Explore Quick Start	er New KeyStore Type
Create a new KeyStore	Open an existing KeyStore	Select the type of the new KeyStore: JCEKS JKS PKCS #12 BKS-V1
Open the CA Certificates KeyStore	Examine a Certificate	O BKS O UBER Cancel OK

2. Generate Key Pair: choose RSA as algorithm with 4096 key size

		📌 📆 📼 Untitled-			
🔳 📄 🔳 Entry Name	Algorithm	Key S	ize	Certificate Expiry	Last Modified
	00	Generate	Key Pair		
	Algorithm Selec	tion			
	💿 RSA	Key Size:		4,096 🗘	
		Key Size:		1,024 🗘	
	⊖ EC	Set:	ANSI X9.62	\$	
	Na	med Curve:	c2tnb191v1	٥	
			Cancel	ОК	
	-				





3. Generate Key Pair Certificate: choose SHA-256 with RSA (version 3) as algorithm with the desired validity period and follow the steps from one to four.



Make sure to type in the actual information related to your Customs office, not the sample values displayed in the screenshot below.

1 📄 🖥	1	X	B.	1	2	発	8	 0	a l	a	0	1)

	A face at the sec		Constituents Frankris	Land March 1974
E Entry Name	Algorithm	Key Size	Generate Key Pair Certificate	Last Modified
		Version:	• Version 1 • Version 3 1	
		Signature Algorithm:	SHA-256 with RSA 🗘	
		Validity Start:	7/9/2020 5:51:35 PM CEST	2
		Validity Period:	1 C Year(s) C Apply	-
		Validity End:	7/9/2021 5:51:35 PM CEST	
		Serial Number:	1594309895	3
		Name:		
0		Name		Add Extensions
Common Name (CN):	Client		+ -	
Organization Unit (OU):	Transport		+ -	Cancel OK 4
Organization Name (O):	ECE		+ -	
Locality Name (L):	GE		+ -	
State Name (ST):	Geneva		+	
Country (C):	СН		- · · ·	
Email (E): Locality Name (L): State Name (ST): 6	etir@un.org		+ -	
Country (C): Email (E): Serial Number (SN): Given Name (GN):			Cancel OK 7	
Surname (SURNAME): Domain Component (DC):				

4. A popup window appears to define an alias for the key pair

	💼 i 📆 🤱 🗍	t 💼 📵 🗄 🕵		
	Ur	ntitled-2 * 🕷		
🔳 📄 🔳 Entry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
	Enter Alias: C	Key Pair Entry Alias ient Cancel		

5. Another popup appears to define a key pair password.



		n 👔 🕺 👔		
	U	ntitled-2 * 🕷		
🔳 📄 🖻 Entry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
	New Ke Enter New Passwo Confirm New Passwo	y Pair Entry Password rd: rd: •••••• Cancel		

6. Key pair generation confirmed.

	📗 🛛 🌠 🗣 🕱 🦷 Un	titled-2 * 🕱	<u>i</u> () <u>i</u> ()	
T E Entry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
n e client	RSA	2048	27/Dec/2019 14:4	27/Dec/2018 14:5
	Ger	nerate Key Pair y Pair Generation Succ	cessful.	

7. Once the key pair generated, click on the save button, a popup window appears to choose the keystore password (it is advised to use another password than for the key pair).





			Q Q :	
	Ur	titled-2 * 🗶		
T E Entry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
📅 🚅 🔍 client	RSA	2048	27/Dec/2019 14:4	27/Dec/2018 14:5
	Set K Enter New Passwor Confirm New Passwor	eyStore Password d: •••••• d: ••••••• Cancel		

8. Specify the keystore name and path (the extension of the file should be ".jks") and then click on the save button.

T E Entr	Save As: Client-keystore	odified
🍿 🛋 🍷 clier	eTIR client	c/2018 14:5
	Name ^ Date Modified	
	File Format: All Files	
	New Folder Cancel Save	

Exporting client's certificate

1. Open the generated keystore from the KeyStore Explorer, right click on the generated key pair, select Export then Export Certificate Chain.



	n · 💦 🤱 🗯	, 📆 📼 🕕 İ 👮]
		client-keystore 🕷		
ntry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
View Detail	s ► #X #C	2048	27/Dec/2019 14:4	27/Dec/2018 14:5
▲ Export	SR Reply cate Chain ト	Export Key Pa Export Certifi Export Private Export Private Export Public	ir <mark>cate Chain</mark> e Key Key	
Sign Unlock Set Passwo Delete Rename	rd			

2. Keep the default values, choose the path of the exported certificate and hit export.

	< → 🕺 🗅	B 77 % % 77			
		clier	it-keystore 🕷		
TEE	Entry Name	Algorithm	Key Size	Certificate Expiry	Last Modified
11 💼 🔍	client	RSA	2048	27/Dec/2019 14:4	27/Dec/2018 14:5
	00	Export Certifica	te Chain from entry 'cl	lient'	
	(
	Export Length:	Head Only O En	tire Chain		
	Export Format:	🖸 Х.509 🛛 🔿 РК	CS #7 OPKI P	ath 🔘 SPC	
	PEM:	V			
	Export File:	eTIR client/client.cer		Bre	owse
				Cancel	xport

12.4.2. Using the Keytool command line interface

The Java Keytool is a command line tool to generate public/private key pairs and store them in a Java KeyStore. Before starting to use the keytool command line, the java bin directory should be added to the path environment variable as shown below:





mputer Name	Hardware	Advanced	System Protecti	on Remote
vironment V	ariables			
·····	<u> </u>			~
Edit Systen	n Variable			
Variable n	ame:	Path		
	-1	1-1-0-10		
Variable v				121 / 0 /0.00
Variable v	alue:	JIO (;C: Prog	ram Files pava y	1k1.7.0_79\bin
Variable v	alue:	JIO (;C: (Prog		Cancel
Variable v	aiue:	JIO (;C: (Prog	OK	Cancel
Variable v	alue:	JIO (;C: (Prog	OK OK	Cancel
Variable v System varia	alue: bles	300 (; C: 1470g	OK	Cancel
Variable v System varia Variable	bles	alue	OK	Cancel
Variable v System varia Variable NUMBER_C	bles Vi DF_P 6	alue	OK	Cancel
Variable v System varia Variable NUMBER_C OS	bles Vi DF_P 6 W	alue		Cancel
Variable v System varia Variable NUMBER_C OS Path	bles DF_P 6 Vi C	alue /indows_NT : \Program File	OK OK es (x86)\VVIDIA	Cancel
Variable v System varia Variable NUMBER_C OS Path PATHEXT	bles Vi DF_P 6 Vi C C	alue /indows_NT : \Program File COM; .EXE; .B/	oK OK es (x86)[WVIDIA AT;.CMD;.VBS;.V	Corpora
Variable v System varia Variable NUMBER_C OS Path PATHEXT	bles Vi)F_P 6 W C (alue /indows_NT : \Program Fill COM; .EXE ; .B/	oK OK es (x86)[WVIDIA AT;.CMD;.VBS;.V	Cancel
Variable v System varia Variable NUMBER_C OS Path PATHEXT	bles V-)F_P6 W C (alue /indows_NT :\Program Fil COM;.EXE;.B/ New	OK OK es (x86)\WVIDIA AT;.CMD;.VBS;.V Edit	Cancel Cancel Corpora BE;.JS; Y

The Keytool executable is called keytool. To execute it, open a command line interface (cmd, console, shell etc.) and change directory into the bin directory of your Java SDK installation. Enter keytool and you should see something similar to this:

C:\Program Files\Java\j Key and Certificate Mar	dk1.8.0_111\bin>keytool magement Tool
Commands:	
-certreq	Generates a certificate request
-changealias	Changes an entry''s alias
-delete	Deletes an entry
-exportcert	Exports certificate
-genkeypair	Generates a key pair
-genseckey	Generates a secret key
-gencert	Generates certificate from a certificate request
-importcert	Imports a certificate or a certificate chain
-importpass	Imports a password
-importkeystore	Imports one or all entries from another keystore
-keypasswd	Changes the key password of an entry
-list	Lists entries in a keystore
-printcert	Prints the content of a certificate -printcertreq Prints the content of a certificate
request	
-printcrl	Prints the content of a CRL file
-storepasswd	Changes the store password of a keystore
Use "keytool -command_r	name -help" for usage of command_name

The Keytool command can take a lot of arguments which may be hard to remember how to set them correctly. Therefore, it is a good idea to create some scripts to simplify the execution of the keytool commands later which also simplifies the maintenance aspects.

Key pair generation

Generating a public/private key pair is one of the most common tasks when using the Keytool. The generated key pair is recorded into a Java KeyStore file as a self-signed key pair. Here is the general command line format for generating a key pair with Keytool:



-genkeypair {-alias alias} {-keyalg keyalg} {-keysize keysize} {-sigalg sigalg} [-dname dname] [-keypass keypass] {validity valDays} {-storetype storetype} {-keystore keystore} [-storepass storepass] {-providerClass
provider_class_name {-providerArg provider_arg}} {-v} {-protected} {-Jjavaoption}

The keystore can be generated using the following set of instructions:

Exporting client's certificate

The Keytool command line can also export certificates stored in a KeyStore. Find below the Keytool command templates for exporting certificates:

```
-exportcert {-alias alias} {-file cert_file} {-storetype storetype} {-keystore keystore} [-storepass storepass] {-
providerName provider_name} {-providerClass provider_class_name {-providerArg provider_arg}} {-rfc} {-v} {-
protected} {-Jjavaoption}
```

In the same folder as the generated Keystore, extract the public key certificate using the following command line and send it to UNECE email addresses (to be stored in the application server's truststore):

keytool -exportcert -keystore ClientKeyStore.jks -alias client -file client.cer -storepass certificatePassword

Hit enter then the certificate will be stored in the same folder as the keystore:

Certificate stored in file <client.cer>





12.5. SOAP UI quick guide

12.5.1. Procedure

Please find below the basic steps required to install and configure the SOAP UI testing tool and for sending an encrypted SOAP request via SoapUI.

- 1. Download and install the SoapUI open-source edition application from SOAP UI website download web page.
- 2. Start the SoapUI application and create a new SOAP project by clicking on File and New SOAP Project. Then, enter a name and set the test URL for the WSDL: https://etir-uat-01.unece.org/etir/v4.3/customs?wsdl

New SOAP Project					
New SOAP Proje Creates a WSDL/	5				
Project Name:	eTIR-Interconnection-UAT				
Initial WSDL:	al WSDL: https://etir-uat-01.unece.org/etir/v4.3/customs?wsdl Browse				
Create Requests: 🗹 Create sample requests for all operations?					
Create TestSuite:	Creates a TestSuite for the imported WSDL				
Relative Paths: Stores all file paths in project relatively to project file (requires save)					
		OK Cancel			

3. After creating a test project, go to the WS-Security Configurations tab inside the 'Show Project View' Menu by right clicking the project folder.

0	SoapU	1 5.5.0											
Eil	e Proje	ct Suite	Case	Step <u>T</u> o	ools <u>D</u> eskto	op <u>H</u> elp							
	Empty	题* SOAP	REST	± Import	Save All	Forum	🛞 Trial	Preferences	Proxy	Endpoint Explo	rer		
itor				•]	🖿 eTIR	-Interconnectio	n-UAT				
Naviga	Projects	eTIR-Interc	onnectio hsSElSecu	n-UAT JreServiceSo	papBinding		Overvie	w TestSuites	WS-Se	curity Configurations	Security Scan Defaults		
					Outgoi	ng WS-Security	Configura	tions Incoming WS-	Security Configurations Keyst	ores Truststores			
		🗄 🗘 get	HolderIn	fo			+ ×						
		🗄 🗘 que	eryGuarar	ntee				Name		Default Username/Alia	Default Password	Actor	
		● ♡ reco ● ♡ refu ● ♡ star ● ♡ star	ordDecla IsalToSta tTIROper ninateTIF	rationData rtTIROperat ation ROperation	ion								

4. Add a KeyStore by clicking the add button and browsing to your keystore file, enter the password and click ok.



💼 eTIR-In	terconnection	I-UAT					r, ⊠, ×
Overview	TestSuites	WS-Security C	Configurations	Security Scan Defaults			
							0
Outgoing	WS-Security C	onfigurations	Incoming WS-	-Security Configurations	Keysto	res Truststores	
+ ×							
	Source		Status	Password		Default Alias	Alias Password
		Select Rechercherg rechercherg Nom du fich Type de fich	Key Material dans : 🗀 key eystore nier : server.ke	stores		V N N N N N N N N N N N N N	

5. Then click on the **Outgoing WS-Security Configurations** tab, to display the configurations that should be applied to outgoing messages, including requests. Add a new outgoing configuration.

eTIR-Interconnection-U/	AT			r, ⊠, ⊠
Overview TestSuites W	S-Security Configurations Se	curity Scan Defaults		
				0
Outgoing WS-Security Confi	igurations Incoming WS-Sec	urity Configurations Keysto	res Truststores	
+×				0
Name	Default Username/Alias	Default Password	Actor	Must Understand
★▼ + X ^ ▼	New Ou	tgoing WSS Configuratic Specify unique name for confi outgoing OK Annuler	on ×	

6. This configuration type is used for encryption, signing and adding SAML, timestamp and username headers. In this situation, only the signing part is used. Add a signature entry.





📕 eTIR-Int	erconnection-l	JAT				r 🖉 🗵
Overview	TestSuites	WS-Security C	onfigurations Se	curity Scan Defaults		
						0
Outgoing	WS-Security Cor	nfigurations	Incoming WS-Sec	urity Configurations Keysto	res Truststores	
+ ×						0
	Name	Default	Username/Alias	Default Password	Actor	Must Understand
outgoing						
			Add W	/SS Entry	×	
+ × ^	*			Select type of entry to add		
		<		Signature	-	
				OK Annuler		
			-			

- 7. Select the keystore and key alias (key) that will be used along with the password for that alias. These are the configurable fields:
 - **Keystore**: the keystore to use when signing the message.
 - Alias: the alias (key pair) to use when signing the message.
 - **Password**: the password of the alias.

📄 eTIR-Int	erconnection-U	AT				r, ⊠, ⊠
Overview	TestSuites V	VS-Security C	onfigurations Se	ecurity Scan Defaults		
						0
Outgoing	WS-Security Con	figurations	Incoming WS-Sec	urity Configurations Keyston	res Truststores	
+ ×						0
	Name	Default	Username/Alias	Default Password	Actor	Must Understand
outgoing						
~~						
+ × ^	*					
Signature		Keystore:		server.keystore 💌		
		Alias:		client alias 🗸]	
		Password:			<i>.</i>	
		Key Identif	ier Type:	Issuer Name and Serial N	umber 💌	
		Signature	Naorithmu			
		Signature				
		Signature	Canonicalization:	<default></default>		_ _
		Digest Alg	orithm:	<default></default>	•	
		Use Single	Certificate:	Use single certificate fo	or signing	
		Prepend Si	gnature Element:	Prepend signature elen	nent to security header (non-s	trict layout)
		Custom Ke	ey Identifier:			L



8. Click on the **Incoming WS-Security Configurations** tab, to configure what should be applied to incoming messages, including responses. Create a new incoming configuration and specify the keystore name and the password. This configuration will ensure the validation of the signature of the incoming responses from eTIR server.

eTIR-Interconnection-UAT			4° 🛛 🖂
Overview TestSuites WS-Securi	ty Configurations Security Scan Del	faults	
			0
Outgoing WS-Security Configuration	Incoming WS-Security Configura	tions Keystores Truststores	
+×			•
Name	Decrypt Keystore	Signature Keystore	Password
incoming		server.keystore	•••••

- 9. Open the SOAP request by right clicking on the **queryGuarantee** request in the treeview on the lefthand side of the application and then select **New request** and give it a name.
- 10. Click the **Auth** tab in the bottom left corner and in the Authorization drop down list, select **Add New Authorization**... and then select **Basic** for a basic authorization.



11. New configuration window appears, select the preconfigured outgoing and incoming WSS.





Authorization:	Basic	0
Username: Password: Domain: Pre-emptive auth:	 Use global preference Authenticate pre-emptively 	
Outgoing WSS: Incoming WSS:	outgoing incoming	

- 12. Switch to the WS-A tab. Make sure that the following settings are properly configured:
 - a. Enable WS-A addressing and ensure the version is 200508;
 - b. Enable 'Randomly generated MessageId;
 - c. Make sure that the action field is correct and looks like the following: etir:v4.3:customs/queryGuarantee

Enable WS-A addressing:		
Must understand:	NONE -	
WS-A Version:	200508 -	
Add default wsa:Action:	Add default wsa:Action	
Action:	etir:v4.3:customs/queryGuarantee	38
Add default wsa:To:	Add default wsa:To	
То:		
Reply to:		
ReplyTo Reference Parameter	5:	
Generate MessagelD:	Randomly generate Messageld	
MessageID:		•
Auth (Basic) Headers	0) Attachments (0) WS-A WS-RM JMS Headers JMS Property (0)	

13. Run SoapUI against the Web Service by passing Soap Messages to the server. You can use the example below:



```
<?xml version="1.0" encoding="UTF-8"?>
<soap:Envelope xmlns:soap="http://www.w3.org/2003/05/soap-envelope"</pre>
               xmlns:cus="etir:v4.3:customs" xmlns:md="etir:DocumentMetaData:v4.3"
               xmlns:urn="etir:I5:v4.3">
    <soap:Header xmlns:wsa="http://www.w3.org/2005/08/addressing">
        <?xml version="1.0" encoding="UTF-8"?>
        (...)
        <wsa:Action>etir:v4.3:customs/queryGuarantee</wsa:Action>
        <wsa:MessageID>uuid:343da525-458e-4f11-a816-ebefc61e004b</wsa:MessageID>
        (...)
    </soap:Header>
    <soap:Body xmlns:wsu="http://docs.oasis-open.org/wss/2004/01/oasis-200401-wss-wssecurity-utility-1.0.xsd"</pre>
               wsu:Id="id-4e410947-cb26-4856-92be-e853433a4783">
        <cus:queryGuarantee>
            <urn:DocumentMetadata>
                <md:ResponsibleAgencyCode>AJ</md:ResponsibleAgencyCode>
                <md:AgencyAssignedCustomizationCode>1</md:AgencyAssignedCustomizationCode>
                <md:AgencyAssignedCustomizationVersionCode>1</md:AgencyAssignedCustomizationVersionCode>
                <md:CommunicationMetaData>
                    <md:PreparationDateTime formatCode="208">20201122113346+0200</md:PreparationDateTime>
                    <md:Recipient>
                        <md:ID>eTIR international system</md:ID>
                    </md:Recipient>
                    <md:Sender>
                        <md:ID>senderID</md:ID>
                    </md:Sender>
                </md:CommunicationMetaData>
                <urn:InterGov>
                    <urn:FunctionCode>9</urn:FunctionCode>
                    <urn:ID>74043437-d6ab-4a79-9bd5-f1f2a8ecc1e2</urn:ID>
                    <urn:TypeCode>I5</urn:TypeCode>
                    <urn:ReplyTypeCode>00</urn:ReplyTypeCode>
                    <urn:ObligationGuarantee>
                        <urn:ReferenceID>XF95001234</urn:ReferenceID>
                    </urn:ObligationGuarantee>
                </urn:InterGov>
            </urn:DocumentMetadata>
        </cus:queryGuarantee>
    </soap:Body>
</soap:Envelope>
```



If you use the feature of SoapUI to automatically generate the XML requests, please note that you need to change the namespace of the DocumentMetadata XML element as displayed in the following image below for the request to be able to work.







12.5.2. Troubleshooting

This section lists potential errors you may encounter and how you can investigate to correct them.

"A security error was encountered when verifying the message"

<soap:envelope xmlns:soap="http://www.w3.org/2003/05/soap-envelope"></soap:envelope>
<soap:header></soap:header>
<pre><action xmlns="http://www.w3.org/2005/08/addressing">etir:v4.3:customs/CustomsSEI/queryGuarantee/Fault/WSSecurityException</action></pre>
<messageid xmlns="http://www.w3.org/2005/08/addressing">urn:uuid:ba3005fd-f5ca-4ce5-83ab-e90b2c56e63a</messageid>
<to xmlns="http://www.w3.org/2005/08/addressing">http://www.w3.org/2005/08/addressing/anonymous</to>
<relatesto xmlns="http://www.w3.org/2005/08/addressing">uuid:46c008ac-8ed2-4b99-b0e7-b2c45e8clc42</relatesto>
<soap:body></soap:body>
<soap:fault></soap:fault>
<soap:code></soap:code>
<soap:value>soap:Sender</soap:value>
<soap:subcode></soap:subcode>
<soap:value xmlns:nsl="http://ws.apache.org/wss4j">nsl:SecurityError</soap:value>
<soap:reason></soap:reason>
<soap:Text xml:lang="en >A security error was encountered when verifying the message< soap:Text>

When receiving the above message in the response from the eTIR international system, please check the following:

- 1. The password for the alias in the outgoing configuration is correct;
- 2. You have sent your certificate to the eTIR Service Desk so it can be registered in the truststore of the eTIR international system.



12.6. Example of SOAP request using WSS4J

The example describes how to use the apache Web Services Security for Java WSS4J to create the SOAP client. The WSS4J project provides a Java implementation of the primary security standards for Web Services, namely the OASIS Web Services Security (WS-Security) specifications from the OASIS Web Services Security TC. WSS4J provides an implementation of X.509 token profile. In this example the signature of the received responses from the eTIR international system can be checked and validated through interceptors, this part is explained in the next section.

First, you need to create your certificate. You can follow one of the two procedures detailed in the section KeyStore: step by step generation of key pairs: using KeyStore Explorer application or the Keytool command line interface.

Create the cryptographic property file

WSS4J requires some cryptographic properties. These properties are grouped in three sections as shown below:

#Crypto properties #General properties: #WSS4J specific provider used to create Crypto instances. Defaults to "org.apache.ws.security.components.crypto.Merlin". #org.apache.ws.security.crypto.provider= #Keystore properties: #The location of the keystore org.apache.ws.security.crypto.merlin.keystore.file=keystoreFile #The password used to load the keystore. Default value is "security". org.apache.ws.security.crypto.merlin.keystore.password=password #Type of keystore. Defaults to: java.security.KeyStore.getDefaultType()), normally it is JKS #org.apache.ws.security.crypto.merlin.keystore.type=JKS #The default keystore alias to use, if none is specified. org.apache.ws.security.crypto.merlin.keystore.alias=aliasName

Password callback handler

The keystore password is specified in the cryptographic properties file as shown in the previous section. However the private key password was not provided yet. In the cryptographic property file there is a property to specify this i.e.

#The default password used to load the private key. Normally it is provided through a password-callback class #org.apache.ws.security.crypto.merlin.keystore.private.password=

A good practice is to provide it through a password callback handler to ensure higher security. The password callback handler can fetch the password from a database, LDAP or from more secured places. In this example, we just display the private key password from the password callback handler class. Find below a basic implementation of the password callback handler:







```
import java.io.IOException;
import javax.security.auth.callback.CallbackHandler;
import javax.security.auth.callback.CallbackHandler;
import javax.security.auth.callback.UnsupportedCallbackException;
import org.apache.ws.security.WSPasswordCallback;
public class ServerPasswordCallback implements CallbackHandler {
    public void handle(Callback[] callbacks) throws IOException, UnsupportedCallbackException {
        for (int i = 0; i < callbacks.length; i++) {
            WSPasswordCallback pc = (WSPasswordCallback) callbacks[i];
            pc.setPassword("key-pass");
        }
    }
}
```

WSS4J Interceptors

The final step is to write the inbound and outbound WSS4J interceptors on the client side. Two interceptors are needed for the SOAP request. The interceptor beans configure the rest of the security settings like, whether the SOAP message will contain timestamp, signature, which parts need to be signed, which algorithm to use, which type of BinarySecurityToken and reference would be used, the pointer to Password Callback Handler class etc. All these settings are configured as key/value pairs in a map. The whole map is listed as WSHandler Tags on the WSS4J configuration page. Please note that many of the keys/settings have default values.

Inbound and outbound WSS4J interceptors - XML-Spring configuration



```
<beans xmlns="http://www.springframework.org/schema/beans"</pre>
xmlns:jaxws="http://cxf.apache.org/jaxws" xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="
http://www.springframework.org/schema/beans http://www.springframework.org/schema/beans/spring-beans.xsd
http://cxf.apache.org/jaxws http://cxf.apache.org/schemas/jaxws.xsd">
<bean id="logInBound" class="org.apache.cxf.interceptor.LoggingInInterceptor" />
<bean id="logOutBound" class="org.apache.cxf.interceptor.LoggingOutInterceptor" />
<jaxws:client id="customsClient" serviceClass="org.unece.etir.ws.cusc.CustomsSEISecure"</pre>
address="https://etir-uat-01.unece.org/etir/v4.3/customs">
<jaxws:inInterceptors>
<ref bean="logInBound" />
<ref bean="inbound-security" />
</jaxws:inInterceptors>
<jaxws:outInterceptors>
<ref bean="logOutBound" />
<ref bean="outbound-security" />
</jaxws:outInterceptors>
</jaxws:client>
<!-- WSS4JOutInterceptor for signing outbound SOAP messages -->
    <bean class="org.apache.cxf.ws.security.wss4j.WSS4JOutInterceptor" id="outbound-security">
        <constructor-arg>
            <map>
                <entry key="action" value="Signature"/>
                <entry key="user" value="client"/>
                <entry key="signaturePropFile" value="client-crypto.properties"/>
                <entry key="passwordCallbackClass" value="client.ClientPasswordCallback"/>
                <entry key="signatureParts"</pre>
                value="{Element}{http://schemas.xmlsoap.org/soap/envelope/}Body"/>
            </map>
        </constructor-arg>
    </bean>
    <!-- WSS4JInInterceptor for validating the signature of inbound SOAP messages -->
    <bean class="org.apache.cxf.ws.security.wss4j.WSS4JInInterceptor" id="inbound-security">
        <constructor-arg>
            <map>
                <entry key="action" value="Signature"/>
                <entry key="signaturePropFile" value="client-crypto.properties"/>
                <entry key="passwordCallbackClass" value="client.ClientPasswordCallback"/>
            </map>
        </constructor-arg>
    </bean>
</heans>
```

Inbound and outbound WSS4J interceptors - Java configuration

WSS4JOutInterceptor signing outbound SOAP messages:

```
Map<String, Object> propsOut = new HashMap<String, Object>();
propsOut.put(WSHandlerConstants.ACTION, WSHandlerConstants.SIGNATURE);
propsOut.put(WSHandlerConstants.SIGNATURE_PARTS, "{Element}{http://www.w3.org/2003/05/soap-envelope}Body;");
propsOut.put(WSHandlerConstants.PW_CALLBACK_CLASS, PasswordCallback.class.getName());
propsOut.put(WSHandlerConstants.USER, "client");
propsOut.put(WSHandlerConstants.SIG_PROP_FILE, "META-INF/client-security.properties");
```

WSS4JInInterceptor validating the signature of inbound SOAP messages:





Map<String, Object> propsIn = new HashMap<String, Object>(); propsIn.put(WSHandlerConstants.ACTION, WSHandlerConstants.SIGNATURE); propsIn.put(WSHandlerConstants.PW_CALLBACK_CLASS, PasswordCallback.class.getName()); propsIn.put(WSHandlerConstants.SIG_PROP_FILE, "META-INF/client-security.properties");

WSS4JOutInterceptor wssOut = new WSS4JOutInterceptor(propsOut); WSS4JInInterceptor wssIn = new WSS4JInInterceptor(propsIn); Client client = ClientProxy.getClient(port); Endpoint endpoint = client.getEndpoint(); endpoint.getOutInterceptors().add(wssOut); endpoint.getInInterceptors().add(wssIn); endpoint.getInInterceptors().add(new LoggingInInterceptor()); endpoint.getOutInterceptors().add(new LoggingOutInterceptor());